

Hardware Setup:

The general structure of electronic hardware is illustrated in Fig. 1. The main controller is a Raspberry Pi 3 Model B, that has a real-time operating system achieved via Preempt-RT patch (<https://rt.wiki.kernel.org/>). A Maxon 70/10 motor drive was employed with Current Control configuration. Analog motor drive commands were sent via an D/A converter (Waveshare 12-bit) which can communicate with the Raspberry Pi unit via SPI (Serial Peripheral Interface). The two 23-bit encoders (Broadcom AS38-H39E-S13S), namely position encoder and torque encoder were utilized to measure motor side angle and spring deflection, respectively. A custom-made PCB was used to transfer encoder data to Raspberry Pi 3 unit via SPI. The circuit schematic and PCB layout were included as the supplementary material. Please see [CustomCircuit_schematic.pdf](#) and [CustomPCB_schematic.pdf](#)




Figure 1: General structure of the electronics hardware.

Software Files:

For each controller, the following C files are provided in a respective folder. When experimentally implementing a controller, make sure that the following files are included in the same folder alongside with `makefile.h` and `myrunner.m`. The respective role of these files are as follows.

`SEALibgen.c` : This script includes the necessary functions that are necessary to use the SEA unit. It is same for all the controllers.

`SEALibgen.h` : It is the header file of `SEALibgen.c`.

`SEALibex.c` : This script includes the controller-specific functions that are necessary to implement the torque controller in question. The duration of the experiment can be set using this script.

SEALibex.h: It is the header file of SEALibex.c.


SEACont.c : This script executes the controller in question. In other words, all the necessary operations are handled in this file, such as, rendering the real-time control, reading of encoders, generating the reference signal, sending motor command signals, and performing necessary mathematical operations



Instructions to Use the Software:

- 1) Complete the connections provided in Fig. 1. Encoders are connected to the custom PCB board. Encoder – PCB connections are tabulated in Table I. Raspberry Pi 3 is connected to the computer via an ethernet cable. Raspberry Pi-3 compatible DAC connections can be obtained from https://www.waveshare.com/wiki/High-Precision_AD/DA_Board. For Maxon 70/10 connections, refer to its hardware manual
- 2) Make sure that the libraries, necessary header files and C files are stored in a designated folder, alongside with the Makefile.h header file.
- 3) The execution of the experiment is initiated via the MATLAB script named myrunner.m
- 4) When myrunner.m is executed, it transfers the necessary .c and .h files to the Raspberry Pi 3 unit.
- 5) Upon the completion of an experiment, all the necessary data are saved to workspace for further investigation.

Table 1: Encoder-Custom PCB Connection

PCB Pin Number	Encoder Cable Color	Cable Function
1	Red	Vcc, Positive Supply (5 V)
2	Black	Ground
3	White	SCL-
4	Brown	SCL+
5	Blue	Dout-
6	Orange	Dout+





Encoder 1

Encoder 2